

OpenDKIM

```
sudo apt install opendkim
```

```
mkdir -p /etc/opendkim/keys
cd /etc/opendkim
touch key.table signing.table trusted.hosts

sudo chown -R opendkim:adm /etc/opendkim
sudo find /etc/opendkim -type d -exec chmod 770 {} \;
sudo find /etc/opendkim -type f -exec chmod 660 {} \;

# socket and permissions
sudo mkdir /var/spool/postfix/opendkim
sudo chown opendkim:postfix /var/spool/postfix/opendkim
sudo chmod 755 /var/spool/postfix/opendkim
```

Example configuration files

The example below shows a configuration for domain.com and domain.net.

Only one selector is in production at a time. This facilitates easy key rotation.

FILE: key.table

```
selector1._domainkey.domain.com    domain.com:selector1:/etc/opendkim/keys/domain.com/selector1.private
selector1._domainkey.domain.net    domain.net:selector1:/etc/opendkim/keys/domain.net/selector1.private
```

```
selector2._domainkey.domain.com    domain.com:selector2:/etc/opendkim/keys/domain.com/selector2.private
selector2._domainkey.domain.net    domain.net:selector2:/etc/opendkim/keys/domain.net/selector2.private
```

FILE: signing.table

```
*@domain.com selector1._domainkey.domain.com  
*@*.domain.com selector1._domainkey.domain.com  
*@domain.net selector1._domainkey.domain.net  
*@*.domain.net selector1._domainkey.domain.net
```

```
*@domain.com selector2._domainkey.domain.com  
*@*.domain.com selector2._domainkey.domain.com  
*@domain.net selector2._domainkey.domain.net  
*@*.domain.net selector2._domainkey.domain.net
```

FILE: trusted.hosts

```
127.0.0.1  
localhost  
  
.domain.com  
.domain.net
```

FILE: /etc/postfix/main.cf

Add the following to your postfix configuration:

```
# DKIM support - Milter configuration  
milter_default_action = accept  
milter_protocol = 6  
smtpd_milters = local:opendkim/opendkim.sock  
non_smtpd_milters = $smtpd_milters
```

FILE: /etc/opendkim.conf

```
# This is a basic configuration for signing and verifying. It can easily be  
# adapted to suit a basic installation. See opendkim.conf(5) and  
# /usr/share/doc/opendkim/examples/opendkim.conf.sample for complete  
# documentation of available configuration parameters.
```

```
Syslog yes  
SyslogSuccess yes
```

```
LogWhy yes

# Common signing and verification parameters. In Debian, the "From" header is
# oversigned, because it is often the identity key used by reputation systems
# and thus somewhat security sensitive.
Canonicalization relaxed/simple

Mode sv

SubDomains no

OversignHeaders From

AutoRestart yes
AutoRestartRate 10/1M
Background yes
DNSTimeout 5
SignatureAlgorithm rsa-sha256

# In Debian, opendkim runs as user "opendkim". A umask of 007 is required when
# using a local socket with MTAs that access the socket as a non-privileged
# user (for example, Postfix). You may need to add user "postfix" to group
# "opendkim" in that case.
UserID opendkim
UMask 007

# Socket for the MTA connection (required). If the MTA is inside a chroot jail,
# it must be ensured that the socket is accessible. In Debian, Postfix runs in
# a chroot in /var/spool/postfix, therefore a Unix socket would have to be
# configured as shown on the last line below.
#Socket local:/run/opendkim/opendkim.sock
#Socket inet:8891@localhost
#Socket inet:8891
Socket local:/var/spool/postfix/opendkim/opendkim.sock

PidFile /run/opendkim/opendkim.pid

# Hosts for which to sign rather than verify, default is 127.0.0.1. See the
# OPERATION section of opendkim(8) for more information.
#InternalHosts 192.168.0.0/16, 10.0.0.0/8, 172.16.0.0/12

# The trust anchor enables DNSSEC. In Debian, the trust anchor file is provided
# by the package dns-root-data.
TrustAnchorFile /usr/share/dns/root.key
```

```
#Nameservers      127.0.0.1

# Map domains in From addresses to keys used to sign messages
KeyTable        refile:/etc/opendkim/key.table
SigningTable    refile:/etc/opendkim/signing.table

# If you ever want to use SQLite3 this is what a dsn would look like
# This being untested, questions remain about the number of slashes needed
# OpenDKIM uses OpenDBX to access alternate database styles
#
# SigningTable dsn:sqlite3:///etc//mail//config.sqlite/table=dkim_keys?keycol=domain?datacol=domain
# KeyTable
dsn:sqlite3:///etc//mail//config.sqlite/table=dkim_keys?keycol=domain?datacol=domain,selector,private_key

# Hosts to ignore when verifying signatures
ExternallgnoreList /etc/opendkim/trusted.hosts

# A set of internal hosts whose mail should be signed
InternalHosts   /etc/opendkim/trusted.hosts

# 20250512
RequireSafeKeys False
```

Revision #2

Created 12 May 2025 16:29:59 by bluecrow76
Updated 12 May 2025 17:33:01 by bluecrow76